



The AccuRoute/Genifax server installation requires a dedicated system that meets the following minimum requirements:

- Windows NT domain computer that always runs in the same domain and is not a domain controller
- Dual core processor; 2 GHz; 4GB of RAM; RAID 5W with 100 GB of disk space; CD-ROM drive; and
- Microsoft mouse or compatible pointing device

*Note Omtool recommends using a core for each compose thread that is configured to do OCR. The AccuRoute/Genifax server comes with 4 Compose threads. You can increase the number of threads as needed. Contact CPI sales for more information.

- Windows 2003 Standard Edition SP2
- IIS with the following components: Common Files, Internet Information Services Manager, SMTP Service (for SMTP connector which is installed with the server) and World Wide Web Service.

*Note In IIS v6.0 or later, configure to allow Active Server Pages. This configuration is located in the Web Service Extensions node in the IIS console tree.

- Disable Internet Explorer Enhanced Security Configuration (Windows Component).

If this component is enabled, you cannot install AccuRoute/Genifax server. After you disable the component, reboot your system before proceeding with the server installation. For instructions on how to verify that the component is disabled, see Verifying that Internet Explorer Enhanced Security Configuration is disabled (2-17)

- Microsoft .Net Framework 2.0 (this is required to install SQL Express 2005 and Exchange2007 connector)
- Exchange 2003/2000 System Manager (for Microsoft Exchange Server integration only)

The AccuRoute server and the Exchange server must be running the same version of this application.

When updates and service packs are applied to the Exchange server, they must be applied to the AccuRoute server also.



* Important - For Exchange 2007, the Exchange server must have a Foreign Connector specified with FAX address type. For general information on Foreign Connector, see <http://technet.microsoft.com/en-us/library/aa996779.aspx>
For information on how to create a Foreign Connector, see <http://technet.microsoft.com/en-us/library/aa996397.aspx>
For information on “Set-ForeignConnector” cmdlet to modify an existing foreign connector, see <http://technet.microsoft.com/en-us/library/bb123789.aspx>

- Notes v5.x / v6.x /v6.5 client (for Notes integration only)

*Note - Do not run any other enterprise application on the AccuRoute server system.

- Microsoft Internet Explorer 6.0 SP1 or later
- Acrobat Reader 5.0 or later
- Internet connection

Click here for the server installation guide:

Server installation

AccuRoute v2.3 server installation guide -

<http://www.omtool.com/documentation/AccuRoute/v23/Server/AccuRouteV23ServerInstallConfigureGuide.pdf>